

**Exhibit Name:** Indemnity Calculations  
**Exhibit Number:** P21-12, Plan 35, 36  
**Record Name:** Acreage Claim  
**Record Code:** P21

**Reinsurance Year:** 2020  
**Version:** Approved  
**Release Date:** 7/1/2019

**Stacked Income Protection**

**Insurance Plan Code** 35 STAX Revenue Protection 36 STAX Revenue Protection with Harvest Price Exclusion

**Commodity Code** 0021 Cotton

Calculations	Field Name	Record Number	Field Number	Field Format	Field Rounding	Rules
<b>Section 1: Stage Guarantee Calculation</b>						
<b>When Insurance plan equals 36:</b>  Acre Stage Guarantee Amount = Dollar Amount of Insurance	Acre Stage Guarantee Amount	P21	58	99999999.99	Round to 2 decimals	
	Dollar Amount of Insurance	Internal		99999999.99	Round to 2 decimals	This will be the Dollar Amount of Insurance determined on the P11. This is for both cotton lint and seed.
<b>When Insurance plan equals 35:</b>  Acre Stage Guarantee Amount = Round(Expected Area Yield * greater of (Projected Price or Harvest Price) * Coverage Range * Price Election Percent, 2)	Acre Stage Guarantee Amount	P21	58	99999999.99	Round to 2 decimals	For cottonseed, this will be the Dollar Amount of Insurance determined on the P11.
	Expected Area Yield	Internal		99999999.99	None	Expected Area Yield. Edit with ADM Price, "A00810", Expected Index Value.
	Projected Price	ADM		99999.9999	None	Edit with ADM Price, "A00810".
	Harvest Price	ADM		99999.9999	None	Edit with ADM Price, "A00810".
	Coverage Range	P14	49	9.9999	2 decimal places	Coverage Range in 5% increments. This would be the Coverage Range used in determination of P11 internal field Dollar Amount of Insurance.  Cottonseed will be Cotton Lint value.
Price Election Percent	P14	35	9.9999	2 decimal places	Protection Factor. Edit with ICE Price Election Percent, "D00007". This will be the Price Election Percent reported on the P14 and used in determination of P11 internal field Dollar Amount of Insurance.  Cottonseed will be Cotton Lint value.	
<b>Section 2: Loss Guarantee Calculation</b>						
Loss Gurantee Amount = Round(Acre Stage Guarantee Amount * Determined Acreage,0) * Insured Share Percent	Loss Guarantee Amount	P21	60	99999999.99	Round to whole number	
	Determined Acreage	P21	18	99999999.99	None	
	Insured Share Percent	P11	43	9.9999	None	

**Exhibit Name:** Indemnity Calculations  
**Exhibit Number:** P21-12, Plan 35, 36  
**Record Name:** Acreage Claim  
**Record Code:** P21

**Reinsurance Year:** 2020  
**Version:** Approved  
**Release Date:** 7/1/2019

**Stacked Income Protection**

**Insurance Plan Code** 35 STAX Revenue Protection 36 STAX Revenue Protection with Harvest Price Exclusion

**Commodity Code** 0021 Cotton

<u>Calculations</u>	<u>Field Name</u>	<u>Record Number</u>	<u>Field Number</u>	<u>Field Format</u>	<u>Field Rounding</u>	<u>Rules</u>
<b>Section 3: Indemnity Calculation</b>						
Preliminary Indemnity Amount = Loss Guarantee Amount * Payment Factor	Preliminary Indemnity Amount	P21	62	S999999999	Round to whole number	
	Payment Factor	ADM		9.999	None	Edit with ADM Area Coverage Level, "A01130".
Indemnity Amount = Preliminary Indemnity Amount * Multiple Commodity Adjustment Factor	Indemnity Amount	P21	63	S999999999	Round to whole number	
	Multiple Commodity Adjustment Factor	ICE		9999.999	None	Edit with ICE Multiple Cropping, "D00063".