Application Source:

File Group:

Record Name: Unknown

Record Code: P98Z

File Type: Delimited

Reinsurance Year: 2023

Version: Approved

Release Date: 7/1/2022

| Record Number | Output | <u>Field</u> Number | <u>Field Name</u> | Data Type | Max Length | <u>Format</u> | BUS Key | Req? | <u>Rules</u> |
|------------------|--------|------------------------|----------------------------|-----------|---------------|--------------------------|------------|------|---|
| P98Z | * | 1 | AIP Code | Character | 2 | | | | AIP Code must be valid; edit with the AIP ICE, "D00100". |
| P98Z | * | 2 | Reinsurance Year | Numeric | 4 | CCYY | | | Reinsurance Year must equal "2023". |
| P98Z | * | 3 | Record Type Code | Character | 6 | | | | Record Type Code must equal "P98Z" |
| P98Z | * | 4 | Overflow Field Number List | Character | 300 | | | | Overflow Field Number List contains the field number of all fields in the input record that exceeded the allowable size for that column in the staging table. |
| P98Z | * | 5 | Malformed Batch Code | Character | 1 | | | | Malformed Batch Code is used to identify the reason a batch was rejected in it's entirety. Malformed Batch Code must equal Malformed File, "M" or Malformed Row, "R". |
| P98Z | * | 6 | Unknown Row Number | Numeric | 15 | | | | Unknown Row Number is a sequential number assigned to each Unknown, "P98Z" record found during processing. Unknown Row Number is unique within the Unknown records for the batch. |
| P98Z | * | 7 | Batch Received Date | Date Time | 21 | CCYYMMDD hh:mm:ss.fff | | | Batch Received Date is the date that the AIP file is received by RMA. |
| P98Z | * | 8 | Batch Number | Numeric | 5 | 99999 | - | | Batch Number is a sequential number assigned when an AIP file is received. |

Application Source:

File Group:

Record Name: Unknown

Record Code: P98Z

File Type: Delimited

Reinsurance Year: 2023

Version: Approved

Release Date: 7/1/2022

| Recor Number | | Field Number | <u>Field Name</u> | Data Type | Max Length | <u>Format</u> | BUS Key | Req? | <u>Rules</u> |
|-----------------|---|-----------------|------------------------|-----------|---------------|----------------|------------|------|--|
| P98Z | * | 9 | Source File Row Number | Numeric | 15 | 99999999999999 | | | Source File Row Number is a unique number assigned by RMA to identify the Row from the Source File where the error occurred. |
| P98Z | * | 10 | Unknown Reason Code | Character | 1 | | | | The Unknown Reason Code is used to identify the reason a single row was rejected. See Unknown Reason ICE, "D00017" for valid values. |