

**Application Source:**  
**File Group:**  
**Record Name: ITS Unknown Reason**  
**Record Code: I98Z**

**File Type: Delimited**  
**Reinsurance Year: 2027**  
**Version: Draft**  
**Release Date: 4/23/2026**

<u>Record Number</u>	<u>Output</u>	<u>Field Number</u>	<u>Field Name</u>	<u>Data Type</u>	<u>Max Length</u>	<u>Format</u>	<u>BUS Key</u>	<u>Req?</u>	<u>Rules</u>
I98Z	*	1	AIP Code	Character	2				AIP Code must be valid; edit with the AIP ICE, "D06100".
I98Z	*	2	Reinsurance Year	Numeric	4	CCYY			Reinsurance Year must equal the Reinsurance Year of the policy for which the debt is due.
I98Z	*	3	Record Type Code	Character	6				Record Type Code must equal "I98Z".
I98Z	*	4	Overflow Field Number List	Character	300				Overflow Field Number List contains the field number of all fields in the input record that exceeded the allowable size for that column in the staging table.
I98Z	*	5	Malformed Batch Code	Character	1				Malformed Batch Code is used to identify the reason a batch was rejected in it's entirety. Malformed Batch Code must equal Malformed File, "M" or Malformed Row, "R".
I98Z	*	6	Unknown Row Number	Numeric	15	999999999999999 999			Unknown Row Number is a sequential number assigned to each Unknown, "P98Z" record found during processing. Unknown Row Number is unique within the Unknown records for the batch.
I98Z	*	7	Batch Received Date	Date Time	21	CCYYMMDD hh:mm:ss.fff			Batch Received Date is the date that the AIP file is received by RMA.

**Application Source:**  
**File Group:**  
**Record Name: ITS Unknown Reason**  
**Record Code: I98Z**

**File Type: Delimited**  
**Reinsurance Year: 2027**  
**Version: Draft**  
**Release Date: 4/23/2026**

<u>Record Number</u>	<u>Output</u>	<u>Field Number</u>	<u>Field Name</u>	<u>Data Type</u>	<u>Max Length</u>	<u>Format</u>	<u>BUS Key</u>	<u>Req?</u>	<u>Rules</u>
I98Z	*	8	Batch Number	Numeric	4	9999			Batch Number is a sequential number assigned when an AIP file is received.
I98Z	*	9	Source File Row Number	Numeric	15	999999999999999 999			Source File Row Number is a unique number assigned by RMA to identify the Row from the Source File where the error occurred.
I98Z	*	10	Unknown Reason Code	Character	1				The Unknown Reason Code is used to identify the reason a single row was rejected. See Unknown Reason ICE, "D00017" for valid values.