Exhibit Name: Premium Calculation

Exhibit Number: P17\_1, Plan 81 Record Name:

Record Code: P17\_1

Reinsurance Year: 2023 Version: Approved

Release Date: 7/1/2022

Insurance Plan Code

81 Livestock Risk Protection

**Commodity Code** 

0801 Feeder Cattle 0802 Fed Cattle 0815 Swine

	<u>Field</u>	Record	<u>Field</u>	<u>Field</u>	<u>Field</u>	
<u>Calculations</u>	<u>Name</u>	<u>Number</u>	<u>Number</u>	<u>Format</u>	Rounding	Rules
Section 1: Liability (Insured Value) Calculation						
Liability Amount = Head Count * Target Weight Quantity * Coverage Price * Insured Share Percent	Liability Amount	P17	43	999999999	Round to whole dollars.	Cupped by the standard rule of \$1 if applicable.
	Head Count	P17	23	99999999	None	
	Target Weight Quantity	P17	24	9999.99	None	Validated against ADM LRP Rate, "A00630," Target Low Rate and Target High Rate.
	Coverage Price	P17	25	9999.999		
	Insured Share Percent	P17	26	9.9999	None	
Section 2: Total Premium, Subsidy, and Producer Premium Calculation						
Total Premium Amount = Liability Amount * Livestock Rate	Total Premium Amount	P17	44	999999999	Round to whole number	Cupped by the standard rule of \$1 if applicable.
	Livestock Rate	ADM		9.999999		Validated against ADM LRP Rate, "A00630."
Subsidy Amount = Total Premium Amount * Subsidy Percent	Subsidy Amount	P17	45	999999999	Round to whole number	
	Subsidy Percent	ADM		9.999	None	Edit with ADM Subsidy Percent, "A00070".
Producer Premium = Total Premium Amount - Subsidy Amount	Producer Premium Amount	P17	48	999999999	Round to whole number	
Section 3: Beginning Farmer and Rancher (BFR), Veteran Farmer Rancher (VFR) and Conservation Compliance (CC) Subsidy Calculations						
	Base Subsidy Amount	Internal		999999999	Round to whole number	Cupped by the standard rule of \$1 if applicable.
Base Subsidy Amount = Total Premium Amount * Subsidy Percent	Subsidy Percent	ADM		9.999	None	Subsidy Factor for LRP will be read off the ADM subsidy rate. Factors are based on coverage level ranges.
BFR/VFR Subsidy Amount = Total Premium Amount * 0.10 * (1 - CC Subsidy Reduction Percent)	BFR/VFR Subsidy Amount	Internal		999999999	Round to whole number	Beginning Farmer Rancher/Veteran Farmer Rancher Subsidy Amount. If Applicable; else 0. 0.10 (10%).
CC Subsidy Reduction = Base Subsidy Amount * CC Subsidy Reduction Percent	CC Subsidy Reduction Percent	P17	33	9.9999	None	If Applicable; else 0.
	CC Subsidy Reduction Amount	P17	42	999999999	Round to whole number	CC Subsidy Reduction Amount. If Applicable; else 0.
Subsidy Amount = Base Subsidy Amount + BFR/VFR Subsidy Amount - CC Subsidy Reduction Amount	Subsidy Amount	P17	45	999999999	Round to whole number	Subsidy Amount cannot exceed Total Premium Amount. Subsidy Amount will be cupped at \$0.
Producer Premium = Total Premium Amount - Subsidy Amount Amount	Producer Premium Amount	P17	48	999999999	Round to whole number	